Instructions for editing the poster

---

1 GETTING STARTED

- **Upload Images:** Drag and drop your logo files and graph images into the project file list (e.g., the left panel in Overleaf).

- **Find Sections:** The code is divided into numbered sections (e.g., `6. GRID`, `7. HEADER`). Use **Ctrl+F** (Windows) or **Cmd+F** (Mac) to search for them.

2 CHANGE TITLE & NAME (Go to Section 7)

1. Scroll down to **Section 7** in the code.

2. Look for the line containing `POSTER TITLE`. Delete the placeholder text and type your own title.

3. Look for `Author One, Author Two`. Type your names there.

4. **Logos:** Find the text `example-image`. Replace it with your exact logo filename (e.g., `iitlogo.png`).

3 PASTE YOUR TEXT (Go to Section 8)

1. Scroll down to **Section 8**. This is where the content boxes are defined.

2. Find a line that looks like this:

```
\createbox{...}{...}{...}{...}{ 1. INTRODUCTION }{ Your text goes here... }
```

3. **Change the Title:** Edit the text `1. INTRODUCTION`.

4. **Change the Text:** Delete `Your text goes here...` and paste your own content.

5. **Tips:**

   - Use \\ to force a new line.
   - Use `\textbf{words}` to make **bold text**.

4 INSERT AN IMAGE (Copy-Paste Code)

To put a picture inside a content box, copy and paste the code below into the content area where you want the image to appear:

```
\begin{center}
  % Change '150mm' to adjust the image height
  \includegraphics[width=\linewidth, height=150mm, keepaspectratio]{your_filename.jpg}
  \captionof{figure}{Write Caption Here}
\end{center}
```

5 RESIZE THE BOXES (Go to Section 6)

If your text doesn't fit or leaves too much empty space, scroll up to **Section 6**.

To make boxes TALLER:

- Find the variable for the row, e.g., \hRowOne (Top Row) or \hRowTwoLeft (Middle Row).

- Change the number (e.g., change 380mm to 420mm).

- **WARNING:** If you make the top row taller, you **must** make the middle or bottom row shorter. The total height of the poster is fixed!

To make columns WIDER:

- Find \colLeft. Increase the number (e.g., 500mm) to make the left column wider. The right column will shrink automatically.

Precaution

- Do **not** change the numbers inside the \createbox{...} lines. (Only edit Section 6 to change sizes).

- Do **not** delete the closing bracket } at the end of a box.